

# Sendoso Connector

Last Modified on 03/11/2024 4:27 am EDT

On this page:

[Authentication Prerequisites](#)

[Required Authentication Parameters](#)

[Connector Fact Sheet and Reference](#)

[Connector API Documentation](#)

[Provider Documentation](#)

## Authentication Prerequisites

The Sendoso connector uses the OAuth 2.0 authentication workflow. To provision an instance with the Sendoso connector all you require is an **OAuth API Key** and **OAuth API Secret**. You need to send an email to [hello@sendoso.com](mailto:hello@sendoso.com) to receive these credentials.

## Required Authentication Parameters

You can authenticate a connector instance using the UI or via API calls. For detailed information on how to authenticate an instance, see our related documentation:

- [Authenticate a Connector Instance \(UI\)](#)
- [Authenticate a Connector Instance \(API\)](#)

To authenticate an instance of the Sendoso connector, you will need the following parameters:

| Parameter Name/UI Value | API Value          | Description                                                                                            | Source                                                  |
|-------------------------|--------------------|--------------------------------------------------------------------------------------------------------|---------------------------------------------------------|
| OAuth API Key           | oauth.api.key      | Provided by Sendoso                                                                                    | <a href="#">Authentication Prerequisites</a>            |
| OAuth API Secret        | oauth.api.secret   | Provided by Sendoso                                                                                    | <a href="#">Authentication Prerequisites</a>            |
| OAuth Callback URL      | oauth.callback.url | Default value is <a href="https://auth.cloudelements.io/oauth">https://auth.cloudelements.io/oauth</a> | <a href="#">Authenticate a Connector Instance (API)</a> |

## Sample Configuration JSON


```
"configuration": {  
  "oauth.api.key": "[myApiKey]",  
  "oauth.api.secret": "[myApiSecret]",  
  "oauth.callback.url": "https://auth.cloudelements.io/oauth"  
}
```

## Connector Fact Sheet and Reference

### Authentication and Configuration Parameters

To see all authentication parameters for the Sendoso connector, follow these steps:

1. Sign in to SAP Open Connectors and navigate to Connectors.
2. Hover over the card for a connector, and then click My Resources.



3. In the top navigation toolbar, click Setup.
4. From the Setup page, you can view a complete list of the connector's authentication and configuration parameters.

### Events and Supported Resources

The Sendoso connector supports events via polling. For detailed information about our Events framework and how to configure a connector instance with events, see our documentation:

- [Authenticate a Connector Instance with Events \(UI\)](#)
- [Authenticate a Connector Instance with Events \(API\)](#)

You can set up polling events for the following resources of the Sendoso connector:

- groups
- return-addresses
- touches

### Queryable Endpoints

You can use OCNQL to query the following endpoints of the Sendoso connector:

- GET /bulk/jobs
- GET /gifts
- GET /{objectName}
- GET /{objectName}/{objectId}/{childObjectName}
- GET /touches
- GET /journals
- GET /payments

- GET /purchase-orders
- GET /tax-rates

## Connector API Documentation

The base URL for all API requests is <https://api.openconnectors.us2.ext.hana.ondemand.com/elements/api-v2> .

## Provider Documentation

- [Sendoso API Documentation](#)
-